SONY

Guidelines of Polling software for FeliCa Certification

Nov 01, 2022

FeliCa Business Division

Copyright 2022 Sony Corporation

Purpose

- Improvement of service to certified businesse
 - Improvement of customer service by shortening measurement time
 - When customer uses debug laboratories, Realize to reduction of measurement work and work time


Solution

One-stop evaluation in which robots and RW


Challenging

Standardizing common commands for Input/Output interface of reader/writer SW


Current evaluation system




Current system configuration diagram



Ideal system configuration



Operation flow chart



Next page explains specifications of #1 to #4

Specification of #1 to #4

#1. Startup/Call

<All items required>

- 1. Windows OS can be called from a BAT file on a console program, and control can be returned to BAT file after the operation is completed.
- 2. If serial communication is used, the serial port must be specifiable as an parameter when calling from a BAT file. (Argument for direct specification in bat file: c COM1)
- 3. Unnecessary arguments can be ignored even if unnecessary arguments are set at the time of invocation.

Note:

Even when the operation is realized through communication control software TeraTerm (TeraTerm macro) etc., all of the requirements in the preceding paragraph must be satisfied. (for example, to create a BAT file that invokes a Tera Term macro.)

RW screen must be operated as a set-up prior to the start of measurement. However, the polling command must be sent and terminated only by the control from the PC without touching RW screen while the communication distance is being measured.

Specification of #1 to #4

#2. Polling command-execution-condition [6.4.3] in the "FeliCa Reader/Writer RF Performance Certification"

<All items required>

1. Parameter condition

System Code: FFFFh, Timeout Time: 200[msec], Time-slot: 00h

Number of runs

Polling must be executed 100 times consecutively within 25 seconds.

- Result judgment condition
 - 1. Success: The test sample can receive Polling normal response packets (including response code and IDm, PMm) within the timeout period for one Polling command transmission.
 - 2. Failed: The test sample for one Polling command transmission is not responding within the timeout period or Polling normal response packet cannot be received.

Specification of #1 to #4

#3 Screen display [6.4.4] [6.4.5] in the "FeliCa Reader/Writer RF Performance Certification Specification"

<All items required>

- 1. Screen display of success failure result
- 2. Count and display of number of consecutive executions/number of successes
- 3. Totaling the correct answer rate and displaying it on the screen

Note:

The screen display of the result should be possible if the situation can be visually confirmed. It can be on the console or on its own GUI display. However, it is desirable that the results can be verified in real time during the study.

#4 Measurement results

<Corresponding to any of the following items>

- 1. Returns the measured result as a return value (correct answer rate for 0-100:Polling command,-1: Abnormal termination of software).
- 2. The software should be able to output measurement results to a log file in text format (e.g., csv file). It is desirable for the caller to be able to specify the output file name of the log output as an argument. To reduce the time and effort required to modify the one-stop batch files, we strongly request that the argument be "f filename" like "polling.exe f data.csv". Also, please describe the type and format of output data in the operation manual. Please refer to page 10.

Ex. Batch file sample with log file

Batch file

```
@echo off
set dist=30
:loop
robot exe c/com5 /d·%dist%
Call polling.exe c com1 f result.csv
echo %dist% >> result.csv
set /a dist = \% dist\% -1
if %dist% GTR 0 goto loop
@echo end of batch file
Output Format of log in your polling software
fprintf s(fp, "%6.2lf%%, %4d, %4d,"
      ,percentage
      ,(total_count - total_error count)
      ,total_count
percentage: Success Rate
(total count - total error count): Success Count
total count: Sending Count
```

Ex. Batch file sample with return values

Batch file

```
@echo off
set dist=30
:loop
robot.exe c/com5 /d:%dist%
Call polling.exe c com1
echo %errorlevel%%%, (100- %errorlevel%), 100, %dist% >> result.csv
set /a dist = \% dist\% -1
if %dist% GTR 0 goto loop
@echo end of batch file
```

In case of "total count=100"

SONY

SONY is a registered trademark of Sony Group Corporation.

Names of Sony products and services are the registered trademarks and/or trademarks of Sony Group Corporation or its Group companies.

Other company names and product names are registered trademarks and/or trademarks of the respective companies.